

# Globale settings for Confluence

En rekke settings er av global art i Confluence. I dette dokumentet dokumenteres hvilke settings som har innvirkning på alle space, samt viser til default settings som er brukt i nåværende installasjon.

- Språk settes globalt
- Installerte plugins er globalt tilgjengelig
- Sikkerhetsinnstillinger

**View Global Permissions**

Configuration

- General Configuration
- Daily Backup Admin
- Manage Referrers
- Plugins
- Plugin Repository
- Languages
- Shortcut Links
- Global Templates
- Mail Servers
- User Macros
- JIRA Issues Icon Mappings
- Attachment Storage
- Spam Prevention
- PDF Language Support
- Default Space Content
- WebDAV Configuration

Look and Feel

- Themes
- Colour Scheme
- Layouts
- Global Logo
- Custom HTML

Theme Builder

- License Details
- Online User Guide
- Theme Administration
- Manage Layouts

Administration

- Backup & Restore
- Content Indexing

**Groups**

These are the global permissions currently assigned to groups.

	Attach Files to User Profile	Personal Space	Create Space(s)	Confluence Administrator	System Administrator
confluence-administrators	can use	can't use	can use	can use	can use
confluence-users	can use	can't use	can use	can't use	can't use

**Individual Users**

These are the global permissions currently assigned to individual users.

No users currently have global permissions.

**Anonymous Access**

When a user is using Confluence while not logged in, they are using it anonymously.  
For example: Enabling anonymous 'USE' permission, allows non-logged-in users to browse pages and spaces in Confluence.

Use Confluence

can't use

**Help Tips**

These permission types are available:

- System Administrator:** Has complete control and access to all administrative functions.
- Confluence Administrator:** Can administer the application but is disallowed from operations that may compromise system security.
- Create Space:** user can add a new space to the site.
- Attach Files to User Profile:** user can upload files to store in their user profile.
- Use Confluence:** user can access this Confluence installation. Without this permission, users will not be able to access to Confluence.

[More about global permissions](#)

**Manage Groups**

Configuration

- General Configuration
- Daily Backup Admin
- Manage Referrers
- Plugins
- Plugin Repository
- Languages
- Shortcut Links
- Global Templates
- Mail Servers
- User Macros
- JIRA Issues Icon Mappings
- Attachment Storage

Look and Feel

- Themes
- Colour Scheme
- Layouts
- Global Logo
- Custom HTML

Theme Builder

- License Details
- Online User Guide
- Theme Administration
- Manage Layouts

Administration

- Backup & Restore
- Content Indexing

Name	Operations
<a href="#">confluence-administrators</a>	<a href="#">Remove</a>
<a href="#">confluence-users</a>	<a href="#">Remove</a>
<a href="#">ubit-administrators</a>	<a href="#">Remove</a>
<a href="#">ubit-users</a>	<a href="#">Remove</a>

**Add Group**

Name:


**Help Tips**

This screen displays the existing user groups on the site and allows you to add new groups. Note that users for the groups are added from the 'Manage Users' screen.

[More about groups](#)


Definering av grupper, med tilhørende aksessrettigheter styres globalt.

- Statistikk genereret via [Global Activity](#) er av global art
- Logging og profilering  
Ytelseslogg, SQL logging og Log4j konfigurasjon er global.
- Unike navn på Themes




Themes som produseres via Theme Builder må ha unike navn, men editering av det gitte theme kan styres via egne sikkerhetsinstillinger. Dvs. en site administrator får ikke default tilgang til et theme som er laget av en administrator for en annen site.

- Globale settings for ThemeBuilder




Editering av global CSS samt "managed layouts" kan medføre endringer for alle spaces.

- Injeksjon av HTML gjøres globalt




- Global logo (men kan overstyres)

- "Site layouts" er globale, men noe kan overstyres av Theme Builder:



- Color Scheme er globalt, men noen innstillinger kan overstyres via Theme Builder



- Global Theme på dashboard gjelder for alle spaces

- Default Space Content

Gjør det mulig å tilpasse hva som vises på hjemmesiden til et nytt space når det opprettes. Tilpassning vil bare gjelde space som er opprettet etter endringen. Eksisterende space vil være uberørt.

- User Macros

Er enkle templatere som er definert av Confluence administratorer. Macroer som defineres her vil være tilgjengelig for alle brukere når de redigerer sider.

- Globalt definerte snarveier

Key	Expanded Value	Default Alias	Operations
cache	http://www.google.com/search?q=cache:		<a href="#">Remove</a>
imdb	http://us.imdb.com/Title?		<a href="#">Remove</a>
googlegroups	http://groups.google.com/groups?q=		<a href="#">Remove</a>
google	http://www.google.com/search?q=		<a href="#">Remove</a>
dictionary	http://www.dict.org/bin/Dict?Database=* & Form=Dict1 & Strategy=* & Query=		<a href="#">Remove</a>



- Generell konfigurasjon

Legg særlig merke til verdier for encoding, datoformat, tallformat

The screenshot shows the 'General Configuration' page in Confluence, specifically the 'Site Configuration' tab. The browser is Mozilla Firefox. The page has a left sidebar with a 'Configuration' menu containing links like 'General Configuration', 'Daily Backup Admin', 'Manage Referrers', 'Plugins', 'Plugin Repository', 'Languages', 'Shortcut Links', 'Global Templates', 'Mail Servers', 'User Macros', 'JIRA Issues Icon Mappings', 'Attachment Storage', 'Spam Prevention', 'PDF Language Support', 'Default Space Content', and 'WebDAV Configuration'. Below this is a 'Look and Feel' section with links for 'Themes', 'Colour Scheme', 'Layouts', 'Global Logo', and 'Custom HTML'. At the bottom is a 'Theme Builder' section with links for 'License Details', 'Online User Guide', 'Theme Administration', and 'Manage Layouts'. The main content area is titled 'Site Configuration' and includes an 'Edit' button. It contains a table with the following settings: 'Site Title' (Confluence), 'Server Base Url' (https://wiki.ntnu.no), 'Site Homepage' (empty), 'Site Welcome Message' (empty), 'View Space Goes to Browse Space' (OFF), and 'Site Support Address' (confluence-autosupportrequests@atlassian.com). Below this table is a 'Feature Settings' section with an 'Edit' button and a table of settings: 'Rich Text Editing' (ON), 'Users see Rich Text Editor by default' (ON), 'CamelCase Links' (OFF), 'Threaded Comments' (ON), 'TrackBack' (OFF), 'Remote API (XML-RPC & SOAP)' (ON), 'Compress HTTP Responses' (OFF), 'Draft Save Interval' (30 seconds), and 'Number of Ancestors to Show in Breadcrumbs' (1). On the right side, there is a 'Help Tips' section with a red icon and text explaining the purpose of the Site Configuration screen. It also includes sections for 'Site Title', 'Site Homepage', 'Site Welcome Message', 'View Space Goes to Browse Space', and 'Site Support Address' with their respective descriptions and default values.

Site Title:	Confluence
Server Base Url:	https://wiki.ntnu.no
Site Homepage:	
Site Welcome Message:	
View Space Goes to Browse Space:	OFF
Site Support Address:	confluence-autosupportrequests@atlassian.com

Rich Text Editing:	ON
Users see Rich Text Editor by default:	ON
CamelCase Links:	OFF
Threaded Comments:	ON
TrackBack:	OFF
Remote API (XML-RPC & SOAP):	ON
Compress HTTP Responses:	OFF
Draft Save Interval:	30 seconds
Number of Ancestors to Show in Breadcrumbs:	1

The screenshot shows the 'General Configuration' page in Confluence, specifically the 'Security and Privacy' tab. The browser is Mozilla Firefox. The page has a left sidebar with a 'Administration' menu containing links like 'Backup & Restore', 'Content Indexing', 'Mail Queue', 'Cache Statistics', 'SnipSnap Import', 'License Details', 'Calendar Administration', 'System Information', 'Support Request', 'Logging and Profiling', 'Global Activity', 'Trusted Applications', and 'LDAP Connectivity Test'. Below this is a 'Security' section with links for 'Manage Users', 'Manage Groups', and 'Global Permissions'. The main content area is titled 'Security and Privacy' and includes an 'Edit' button. It contains a table with the following settings: 'External user management' (OFF), 'Public Signup' (OFF), 'Hide External Links From Search Engines' (ON), 'User email visibility' (public), 'Anonymous Access to Remote API' (OFF), and 'Anti XSS Mode (Experimental)' (OFF). Below this table is a 'Formatting and International Settings' section with an 'Edit' button and a table of settings: 'Encoding' (UTF-8), 'Indexing Language' (other), 'Time Format' (hh:mm a (01:24 PM)), 'Day Format' (MMM dd (Aug 28)), 'Date Time Format' (MMM dd, yyyy HH:mm (Aug 28, 2008 13:24)), 'Date Format' (MMM dd, yyyy (Aug 28, 2008)), 'Long Number Format' (#####), 'Decimal Number Format' (#####), and 'Show Link Icons' (OFF). On the right side, there is a 'Help Tips' section with a red icon and text explaining the purpose of the Security and Privacy screen. It also includes sections for 'Enable Rich Text Editing', 'Users see Rich Text Editor by default', 'Camel Case Links', 'Threaded Comments', and 'TrackBack' with their respective descriptions and default values.

External user management:	OFF
Public Signup:	OFF
Hide External Links From Search Engines:	ON
User email visibility:	public
Anonymous Access to Remote API:	OFF
Anti XSS Mode (Experimental):	OFF

Encoding:	UTF-8
Indexing Language:	other
Time Format:	hh:mm a (01:24 PM)
Day Format:	MMM dd (Aug 28)
Date Time Format:	MMM dd, yyyy HH:mm (Aug 28, 2008 13:24)
Date Format:	MMM dd, yyyy (Aug 28, 2008)
Long Number Format:	#####
Decimal Number Format:	#####
Show Link Icons:	OFF

General Configuration - Confluence - Mozilla Firefox

File

Rediger

Vis

Hjstørrelsk

Bokmerker

Verktøy

Hjelp

https://wiki.ntnu.no/admin/viewgeneralconfig.action

Mest besøkt

Disable Cookies CSS Forms Images Information Miscellaneous Outline Resize Tools View Source Options

Attachment Settings

Edit

You can configure where attachments are stored on the [attachment storage page](#)

Attachment Maximum Size (B):	10.00 MB
Maximum Attachments per Upload:	5
Thumbnail maximum height:	200
Thumbnail maximum width:	200

Connection Timeouts

Edit

External connections enabled :	true
Connection Timeout (milliseconds) :	10000
Socket Timeout (milliseconds) :	10000

versa.

Default: OFF

[More about Trackback](#)

**Remote API:**

Enabling the remote APIs allows you to access Confluence remotely.

Default: ON

[More about Remote APIs](#)

**Draft Save Interval:**

Allows you to configure the time for how often drafts are saved.

Default: 30 Seconds

**External User Management:**

Enable this option if you are delegating your user management to JIRA.

Default: OFF

[More about User Management](#)

**Public Signup:**

Enabling Public Signup will allow users to sign themselves up to the site as a new user.

Default: ON

[More about Public Signup](#)

**Hide External Links From Search Engines:**

Enabling this option will give the "nofollow" attribute to external links

Fullbart

wiki.ntnu.no